

# KVM\_Vswitch 模式部署 Supernova

## (界面方式和命令行方式)

网测科技

2023.03.01

# 目录

KVM 介绍 .....	4
1. 安装 KVM 前准备 .....	4
1.1 安装 CentOS 系统时注意： .....	4
1.2 禁用它如下:.....	4
1.3 系统安装成功后验证 CPU 是否支持 KVM, 如果结果中带有 VMX (INTEL) 或 SVM (AMD) 说明支持.....	5
1.4 在 BIOS 中开机虚拟化功能 .....	5
1.5 关闭 XELinux.....	6
2. 安装 KVM .....	6
2.1 安装 KVM 包 .....	6
2.2 安装 KVM 核心包——虚拟操作系统模拟器加速模块 .....	6
2.3 重启宿主机, 加载 KVM 相关模块.....	6
2.4 查看 KVM 模块是否被正确加载 .....	6
2.5 开启 KVM 服务, 并设置开机启动.....	7
2.6 查看操作结果, 出现 Active: active (running) 字样则说明运行情况良好 .....	7
2.7 如果执行开启 KVM 服务报错请更新系统 .....	7
3. 配置 KVM .....	7
3.1 添加存储池.....	8
3.2 创建虚拟机.....	11
3.3 增加一块 Data 盘 (Supernova 默认要用到两块硬盘) .....	14
3.4 增加网卡 .....	17
3.5 调整 CPU 和内存大小.....	19
4. 启动 Supernova .....	20
4.1 运行虚拟机.....	20
4.2 成功运行后测试仪 dhcp 自动获取 IP 地址 .....	22
4.3 登陆 Supernova 测试能否访问和运行用例 .....	22
5. 使用命令行方式部署虚拟机 .....	24
5.1 创建 vswitch 文件夹 .....	24
5.2 进入该目录上传镜像 .....	24
5.3. 创建 vswitch 的池并启动 .....	24
5.4. 上传虚拟机的 xml 文件 .....	25
5.6 启动虚拟机 .....	26
6. 附加: VNC 配置方法 .....	27
6.1 安装软件包 .....	28
6.2 关闭防火墙 .....	28
6.3 复制配置文件 .....	28
6.4 编辑复制出来的配置文件 .....	28
6.5 重新加载配置文件 .....	28
6.6 设置 VNC 密码 .....	28
6.7 开启 VNC 并设置成开机启动 .....	29
6.8 启动 .....	29
6.9 如果启动成功端口是监听状态(VNC 端口号默认 5900+1).....	29

6.10 客户端连接 .....	29
------------------	----

# KVM 介绍


KVM 是 Kernel-based Virtual Machine 的简称，是一个开源的系统虚拟化模块，自 Linux 2.6.20 之后集成在 Linux 的各个主要发行版本中。它使用 Linux 自身的调度器进行管理。KVM 目前已成为学术界的主流 VMM 之一。

KVM 的虚拟化需要硬件支持(如 Intel VT 技术或 AMD V 技术)。是基于硬件的完全虚拟化。

下文是将 Supernova 部署到桥接模式 KVM 的部署方法  
宿主机：就是实体机

## 1. 安装 KVM 前准备

### 1.1 安装 CentOS 系统时注意：



### 1.2 禁用它如下：

命令：chkconfig NetworkManager off

命令：chkconfig network on

命令：service NetworkManager stop

## 1.3 系统安装成功后验证 CPU 是否支持 KVM，如果结果中带有 VMX (INTEL) 或 SVM (AMD) 说明支持

命令：cat /proc/cpuinfo | egrep 'vmx|svm'


效果：

```
[root@localhost ~]# egrep '(vmx|svm)' /proc/cpuinfo
flags    : fpu vme de pse tsc msr pae mce cx8 apic sep mtrr pge mca cmov pat pse36 clflush dts acpi mmx fxsr sse sse2 ss ht tm pbe syscall nx pdpe1gb rdtscp lm constant_tsc art arch_perfmon pebs bts rep_good nopl xtopology nonstop_tsc aperfmpf eagerfpu pni pcimulqddq dtes64 monitor ds_cpl l vmx smx est tm2 sse3 fma cx16 xtr pdcm pcid sse4_1 sse4_2 x2apic movbe popcnt tsc_deadline_timer aes xsave avx f16c rdrand lahf_lm abm 3dnowprefetch etch epb intel_pt tpr_shadow vnmi flexpriority ept vpid fsgsbase tsc_adjust bmi1 hle avx2 smp bmi2 erms invpcid rtm mpx rdseed adx smap clflushopt xsaveopt xsavc xgetbv1 dtherm ida arat pln pts hwp hwp_notify hwp_act_window hwp_epp
flags    : fpu vme de pse tsc msr pae mce cx8 apic sep mtrr pge mca cmov pat pse36 clflush dts acpi mmx fxsr sse sse2 ss ht tm pbe syscall nx pdpe1gb rdtscp lm constant_tsc art arch_perfmon pebs bts rep_good nopl xtopology nonstop_tsc aperfmpf eagerfpu pni pcimulqddq dtes64 monitor ds_cpl l vmx smx est tm2 sse3 fma cx16 xtr pdcm pcid sse4_1 sse4_2 x2apic movbe popcnt tsc_deadline_timer aes xsave avx f16c rdrand lahf_lm abm 3dnowprefetch etch epb intel_pt tpr_shadow vnmi flexpriority ept vpid fsgsbase tsc_adjust bmi1 hle avx2 smp bmi2 erms invpcid rtm mpx rdseed adx smap clflushopt xsaveopt xsavc xgetbv1 dtherm ida arat pln pts hwp hwp_notify hwp_act_window hwp_epp
flags    : fpu vme de pse tsc msr pae mce cx8 apic sep mtrr pge mca cmov pat pse36 clflush dts acpi mmx fxsr sse sse2 ss ht tm pbe syscall nx pdpe1gb rdtscp lm constant_tsc art arch_perfmon pebs bts rep_good nopl xtopology nonstop_tsc aperfmpf eagerfpu pni pcimulqddq dtes64 monitor ds_cpl l vmx smx est tm2 sse3 fma cx16 xtr pdcm pcid sse4_1 sse4_2 x2apic movbe popcnt tsc_deadline_timer aes xsave avx f16c rdrand lahf_lm abm 3dnowprefetch etch epb intel_pt tpr_shadow vnmi flexpriority ept vpid fsgsbase tsc_adjust bmi1 hle avx2 smp bmi2 erms invpcid rtm mpx rdseed adx smap clflushopt xsaveopt xsavc xgetbv1 dtherm ida arat pln pts hwp hwp_notify hwp_act_window hwp_epp
flags    : fpu vme de pse tsc msr pae mce cx8 apic sep mtrr pge mca cmov pat pse36 clflush dts acpi mmx fxsr sse sse2 ss ht tm pbe syscall nx pdpe1gb rdtscp lm constant_tsc art arch_perfmon pebs bts rep_good nopl xtopology nonstop_tsc aperfmpf eagerfpu pni pcimulqddq dtes64 monitor ds_cpl l vmx smx est tm2 sse3 fma cx16 xtr pdcm pcid sse4_1 sse4_2 x2apic movbe popcnt tsc_deadline_timer aes xsave avx f16c rdrand lahf_lm abm 3dnowprefetch etch epb intel_pt tpr_shadow vnmi flexpriority ept vpid fsgsbase tsc_adjust bmi1 hle avx2 smp bmi2 erms invpcid rtm mpx rdseed adx smap clflushopt xsaveopt xsavc xgetbv1 dtherm ida arat pln pts hwp hwp_notify hwp_act_window hwp_epp
[root@localhost ~]#
```

## 1.4 在 BIOS 中开机虚拟化功能

方法：开启按 delete 键进入 BIOS 中--用键盘方向键选中“Advanced”菜单--选中“CPU Configuration”—找到“Intel Virtualization Technology”开启

效果：



## 1.5 关闭 XELinux

命令：vi /etc/sysconfig/selinux

效果：

```
# This file controls the state of SELinux on the system.
# SELINUX= can take one of these three values:
#       enforcing - SELinux security policy is enforced.
#       permissive - SELinux prints warnings instead of enforcing.
#       disabled - No SELinux policy is loaded.
SELINUX=disabled
# SELINUXTYPE= can take one of three two values:
#       targeted - Targeted processes are protected,
#       minimum - Modification of targeted policy. Only selected processes are protected.
#       mls - Multi Level Security protection.
SELINUXTYPE=targeted
```

## 2. 安装 KVM

### 2.1 安装 KVM 包

命令：yum -y install kvm

### 2.2 安装 KVM 核心包——虚拟操作系统模拟器加速模块

命令：yum -y install qemu-kvm qemu-kvm-tools

命令：yum -y install libvirt python-virtinst libvirt-python virt-manager libguests-tools bridge-utils virt-install

说明：

libvirt：必须要装的核心工具

python-virtinst：包含 python 模块和工具（virt-install, virt-clone 和 virt-image）

virt-manager：虚拟机图形管理工具（宿主机有桌面环境时可以考虑安装，命令操作或者远程控制则不需要）

bridge-utils：虚拟机与外界通信的命令管理工具

virt-install：虚拟机安装工具

### 2.3 重启宿主机，加载 KVM 相关模块

命令：reboot

### 2.4 查看 KVM 模块是否被正确加载

命令：lsmod | grep kvm

出现以下信息则表示正确加载。

```
[root@localhost ~]# lsmod | grep kvm
kvm_intel           183621  0
kvm                 586948  1 kvm_intel
irqbypass          13503   1 kvm
[root@localhost ~]#
```

## 2.5 开启 KVM 服务，并设置开机启动

命令：systemctl start libvirtd.service (开启) (如报错请看 2.7)

命令：systemctl enable libvirtd.service (开机启动)

## 2.6 查看操作结果，出现 Active: active (running) 字样则说明运行情况良好

命令：systemctl status libvirtd (启动状态)

命令：systemctl is-enabled libvirtd (是否开机自动启动)

效果：

```
[root@localhost ~]# systemctl status libvirtd
● libvirtd.service - Virtualization daemon
   Loaded: loaded (/usr/lib/systemd/system/libvirtd.service; enabled; vendor preset: enabled)
   Active: active (running) since — 2019-01-14 18:04:47 CST; 18min ago
     Docs: man:libvirtd(8)
           https://libvirt.org
 Main PID: 6050 (libvirtd)
   Tasks: 19 (limit: 32768)
  CGroup: /system.slice/libvirtd.service
          └─6050 /usr/sbin/libvirtd
              ├─8500 /usr/sbin/dnsmasq --conf-file=/var/lib/libvirt/dnsmasq/default.conf --leasefile-ro --dhcp-script
              ├─8501 /usr/sbin/dnsmasq --conf-file=/var/lib/libvirt/dnsmasq/default.conf --leasefile-ro --dhcp-script
              └─8502 /usr/sbin/dnsmasq --conf-file=/var/lib/libvirt/dnsmasq/default.conf --leasefile-ro --dhcp-script

1月 14 18:04:47 localhost.localdomain systemd[1]: Started Virtualization daemon.
1月 14 18:04:52 localhost.localdomain dnsmasq[8500]: started, version 2.76 cachesize 150
1月 14 18:04:52 localhost.localdomain dnsmasq[8500]: compile time options: IPv6 GNU-getopt DBus no-i18n IDN DHCP
1月 14 18:04:52 localhost.localdomain dnsmasq-dhcp[8500]: DHCP, IP range 192.168.122.2 -- 192.168.122.254, lease
1月 14 18:04:52 localhost.localdomain dnsmasq[8500]: DHCP, sockets bound exclusively to interface virbr0
1月 14 18:04:52 localhost.localdomain dnsmasq[8500]: reading /etc/resolv.conf
1月 14 18:04:52 localhost.localdomain dnsmasq[8500]: using nameserver 180.76.76.76#53
1月 14 18:04:52 localhost.localdomain dnsmasq[8500]: read /etc/hosts - 2 addresses
1月 14 18:04:52 localhost.localdomain dnsmasq[8500]: read /var/lib/libvirt/dnsmasq/default.addnhosts - 0 address
1月 14 18:04:52 localhost.localdomain dnsmasq-dhcp[8500]: read /var/lib/libvirt/dnsmasq/default.hostsfile
Hint: Some lines were ellipsized, use -l to show in full.
```

```
[root@localhost ~]# systemctl is-enabled libvirtd
enabled
[root@localhost ~]#
```


## 2.7 如果执行开启 KVM 服务报错请更新系统



命令：yum -y update



```
[root@localhost ~]# systemctl start libvirtd.service
Job for libvirtd.service failed because the control process exited with
error code. See "systemctl status libvirtd.service" and "journalctl -xe"
for details.
[root@localhost ~]#
```

## 3. 配置 KVM


### 3.1 添加存储池







注意：从 23.03 版本开始需要手动创建数据盘  
用 23.03 以后版本解压出的文件为 README 和系统盘 boot.qcow2



打开终端执行创建数据盘命令


The terminal window shows the command to create a 40G empty disk:


```
Create 40G empty disk by following command:  
# qemu-img create -f qcow2 -o preallocation=full ./data.qcow2 40G
```

Output of the ls command:

```
[root@localhost ~]# qemu-img create -f qcow2 -o preallocation=full ./data.qcow2 40G  
Formatting './data.qcow2', fmt=qcow2 size=42949672960 encryption=off cluster_size=65536 preallocation='full' lazy_refcounts=off  
[root@localhost ~]# ls  
anaconda-ks.cfg data.qcow2 README 公共 视频 文档 音乐  
boot.qcow2 initial-setup-ks.cfg root 模板 图片 下载 桌面  
[root@localhost ~]#
```

### 3.2 创建虚拟机





**新建虚拟机**

生成新虚拟机  
4 的步骤 2



提供现有存储路径(G) :

浏览(R)...

**选择存储卷**



卷	大小	格式	用于
boot.qcow2	396.58 MiB	qcow2	Vswitch
data.qcow2	30.00 GiB	qcow2	Vswitch



This screenshot shows the second step of the wizard, where it asks for an existing storage path. A 'Browse...' button is highlighted with a red box. Below, a table lists existing storage volumes: 'boot.qcow2' (396.58 MiB, qcow2, Vswitch) and 'data.qcow2' (30.00 GiB, qcow2, Vswitch). The 'Vswitch' volume is also highlighted with a red box.





在创建虚拟机的过程中第一块 Boot 盘就有了

### 3.3 增加一块 Data 盘 (Supernova 默认要用到两块硬盘)









### 3.4 增加网卡


添加管理口 mgmt1 网卡，点击添加硬件-网络，网络源选择 br0，设备型号选择 e1000，作为 mgmt1 管理口，设置后点击完成以完成网卡添加。




添加管理口 mgmt2 网卡，点击添加硬件-网络，网络源选择主机其他可用网卡，如 enp2s0f0，设备型号选择 e1000，作为 mgmt2 管理口，设置后点击完成以完成网卡添加。




添加测试口 port1 网卡，点击添加硬件-网络，网络源选择主机其他可用网卡，如 enp4s0f0，源模式选择桥接，设备型号选择 virtio，作为 port1 测试口，设置后点击完成完成网卡添加。




添加测试口 port2 网卡，点击添加硬件-网络，网络源选择主机其他可用网卡，如 enp4s0f1，源模式选择桥接，设备型号选择 virtio，作为 port2 测试口，设置后点击完成完成网卡添加。



网卡配置完成后效果如下：





### 3.5 调整 CPU 和内存大小



## 4. 启动 Supernova

### 4.1 运行虚拟机





注：如果在启动过程中报 port1/port2 错误，进入到页面后发现刚报出错误的 port 没有显示出来那么请在 cd /etc/sysconfig/network-scripts 中加入相对应的接口。

先查看我 4 个 10G 口的网卡名称：

```
[root@localhost network-scripts]# ifconfig -a
br0: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.168.16.95 netmask 255.255.255.0 broadcast 192.168.16.255
        inet6 fe80::8ad7:f6ff:fec4:216f prefixlen 64 scopeid 0x20<link>
            ether 88:d7:f6:c4:21:6f txqueuelen 1000 (Ethernet)
            RX packets 2707 bytes 189894 (185.4 KiB)
            RX errors 0 dropped 0 overruns 0 frame 0
            TX packets 532 bytes 91021 (88.8 KiB)
            TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

enp0s31f6: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet6 fe80::8ad7:f6ff:fec4:216f prefixlen 64 scopeid 0x20<link>
        ether 88:d7:f6:c4:21:6f txqueuelen 1000 (Ethernet)
        RX packets 3452 bytes 462497 (451.6 KiB)
        RX errors 0 dropped 10 overruns 0 frame 0
        TX packets 547 bytes 95489 (93.2 KiB)
        TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
    1 device interrupt 16 memory 0xd400000-df420000

enp1s0f0: flags=4098<BROADCAST,MULTICAST> mtu 1500
    ether 68:91:d0:61:be:cc txqueuelen 1000 (Ethernet)
    RX packets 0 bytes 0 (0.0 B)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 0 bytes 0 (0.0 B)
    2 TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

enp1s0f1: flags=4098<BROADCAST,MULTICAST> mtu 1500
    ether 68:91:d0:61:be:cd txqueuelen 1000 (Ethernet)
    RX packets 0 bytes 0 (0.0 B)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 0 bytes 0 (0.0 B)
    3 TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

enp4s0f0: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet6 fe80::216:31ff:fe00:4942 prefixlen 64 scopeid 0x20<link>
        ether 00:16:31:f2:49:42 txqueuelen 1000 (Ethernet)
        RX packets 1 bytes 78 (78.0 B)
        RX errors 0 dropped 0 overruns 0 frame 0
        TX packets 0 bytes 0 (0.0 B)
        4 TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

enp4s0f1: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet6 fe80::216:31ff:fe00:4943 prefixlen 64 scopeid 0x20<link>
        ether 00:16:31:f2:49:43 txqueuelen 1000 (Ethernet)
        RX packets 1 bytes 78 (78.0 B)
        RX errors 0 dropped 0 overruns 0 frame 0
        TX packets 0 bytes 0 (0.0 B)
```

在 `cd /etc/sysconfig/network-scripts` 中要一一对应；如果没有对应需要手动添加：

```
[root@localhost ~]# cd /etc/sysconfig/network-scripts/
[root@localhost network-scripts]$ ls
ifcfg-br0          ifdown-ib      ifdown-ppp      ifdown-tunnel  ifup-ib      ifup-plusb    ifup-Team      network-functions
ifcfg-ens3f6        ifcfg-lo      ifdown-ipp     ifdown-routes  ifup         ifup-ipp       ifup-TeamPort   network-functions-ipv6
ifcfg-ens3f0        ifdown        ifdown-ipv6    ifdown-sit     ifup-aliases  ifup-ppp       ifup-tunnel
ifcfg-ens3           ifdown-bnep   ifdown-isdn   ifdown-Team    ifup-bnep    ifup-isdn     ifup-wireless
ifcfg-ens3f0        ifdown-eth   ifdown-post   ifdown-TeamPort  ifup-eth    ifup-sit      init.ipv6-global
[root@localhost network-scripts]$
```

这是我的四块 10G 网卡，我用到的是 ifcfg-enp4s0f0 和 ifcfg-enp4s0f1 如果这个表中没有这两个是需要添加的添加的内容为：

```
vi ifcfg-enp4s0f0
```


```
BOOTPROTO=none  
IPV6INIT=yes  
IPV6_AUTOCONF=yes  
DEVICE=enp4s0f0  
ONBOOT=yes
```

#### 4.2 成功运行后测试仪 dhcp 自动获取 IP 地址

```
Entering listen mode: raw
Opening raw socket on if index 5
Got raw socket fd
Attached filter to raw socket fd
Created raw socket
Adapter index 5
MAC 52:54:00:ed:55:3b
Sending discover...
Waiting on select 3 seconds
Received a packet
Adapter index 5
MAC 52:54:00:ed:55:3b
Sending select for 192.168.18.45...
Waiting on select 3 seconds
Received a packet
Lease of 192.168.18.45 obtained, lease time 604800
Executing /usr/share/udhcpc/default.script bound
deleting routers
Entering listen mode: none
Version: 22.12.11 build2907
Build date: 20230225
kernel version: 5.10.112
System is started.
```

#### 4.3 登陆 Supernova 测试能否访问和运行用例

通过设置的管理 IP 访问 web 管理页面，初始登录账号密码：admin/admin



## 测试创建运行用例

This screenshot shows the Supernova-KVM software during the execution of a test case named "UdpPps\_TP\_admin\_20210106-16:05:46". The interface includes several monitoring and management panels:

- 关键结果**: Displays statistics for UDP traffic on Port 2 and Port 4, including receive and transmit counts.
- 报文捕获**: Shows captured traffic details for Port 2 and Port 4.
- 系统资源**: Monitors system memory usage.
- 状态**: Provides a summary of the test status.
- 网地址**: Shows network address information for Port 2 and Port 4.
- 路数据**: Displays route data for Port 2 and Port 4.
- 用例管理**: Manages the test case.

At the bottom, it shows "运行状态: 正在运行" (Running) and "运行时间: 00:00:37".

## 5. 使用命令行方式部署虚拟机

### 5.1 创建 vswitch 文件夹

```
[root@localhost home]# cd /home          进入到 home 目录下
[root@localhost home]# mkdir vswitch      创建 vswitch 文件夹
[root@localhost home]# ls
[root@localhost home]# mkdir vswitch
[root@localhost home]# ls
CLD pass-through PASSTHROUGH tester vswitch
```

### 5.2 进入该目录上传镜像

NOVA\_VM\_CLD-HW01-v22.12.11-build2907-20230225.img.cloud.zip

```
[root@localhost ~]# cd /home/vswitch      进入到/home/vswitch 文件夹下
[root@localhost vswitch]# rz          上传镜像文件
[root@localhost vswitch]# rz
rz waiting to receive.
Starting zmodem transfer. Press Ctrl+C to cancel.
Transferring NOVA_VM_CLD-HW01-v22.12.11-build2907-20230225.img.cloud.zip...
100% 604313 KB    10242 KB/sec   00:00:59      0 Errors
```

unzip 命令解压镜像

```
[root@localhost vswitch]# unzip NOVA_VM_CLD-HW01-v22.12.11-build2907-
20230225.img.cloud.zip
```

**注意：从 23.03 版本开始需要手动创建数据盘**

用 23.03 以后版本解压出的文件为 README 和系统盘 boot.qcow2

```
[root@localhost vswitch]# unzip NOVA_VM_CLD-HW01-v23.03.06-build3094-20230321-x86_64.img.cloud.zip
Archive: NOVA_VM_CLD-HW01-v23.03.06-build3094-20230321-x86_64.img.cloud.zip
  inflating: README
  inflating: boot.qcow2
[root@localhost vswitch]#
```

README 内容为创建数据盘命令

```
[root@localhost vswitch]# cat README
Create 40G empty disk by following command:
# qemu-img create -f qcow2 -o preallocation=full ./data.qcow2 40G 执行创建数据盘命令
[root@localhost vswitch]# qemu-img create -f qcow2 -o preallocation=full ./data.qcow2 40G
Formatting './data.qcow2', fmt=qcow2 size=42949672960 encryption=off cluster_size=65536 preallocation='full' lazy_refcounts=off
[root@localhost vswitch]# ls
boot.qcow2 data.qcow2 NOVA_VM_CLD-HW01-v23.03.06-build3094-20230321-x86_64.img.cloud.zip README
[root@localhost vswitch]#
```

### 5.3. 创建 vswitch 的池并启动

```
[root@localhost vswitch]# virsh----进入 virsh 工具
virsh # pool-define-as vswitch dir --target '/home/vswitch/' -----定义池 vswitch
virsh # pool-build vswitch-----构建池 vswitch
virsh # pool-start vswitch-----启动池 vswitch
virsh # pool-autostart vswitch-----池 vswitch 标记为自动启动
```

```
virsh # pool-list --all -----查看池运行状态  
virsh #pool-refresh vswitch-----刷新池  
virsh # pool-build vswitch  
构建池 vswitch  
virsh # pool-start vswitch  
池 vswitch 已启动  
virsh # pool-autostart vswitch  
池 vswitch 标记为自动启动  
virsh # pool-list --all  
名称 状态 自动开始  
-----  
CLD-1 活动 是  
default 活动 是  
PASS-THROUGH 活动 否  
pass-through 活动 是  
vswitch 活动 是  
virsh # pool-refresh vswitch  
池 vswitch 被刷新
```

#### 5.4.上传虚拟机的 xml 文件



```
[root@localhost ~]# cd /etc/libvirt/qemu/  
rz 上传 novavm.xml  
[root@localhost qemu]# rz  
rz waiting to receive.  
Starting zmodem transfer. Press Ctrl+C to cancel.  
Transferring vswitch.xml...  
vswitch.xml was skipped
```

修改文件内容调整虚拟机配置

```
[root@localhost ~]# vim /etc/libvirt/qemu/vswitch.xml
```

```
<domain type='kvm'>
  <name>vswitch</name>
  <uuid>2905e69c-7d99-4a11-9a32-36a728a0a16c</uuid>
  <memory unit='KiB'>8388608</memory>
  <currentMemory unit='KiB'>8388608</currentMemory>
  <vcpu placement='static' value='4' vcpu>
  <os>
    <type arch='x86_64' machine='pc-i440fx-rhel7.0.0'>hvm</type>
    <boot dev='hd' />
  </os>
  <features>
    <acpi />
    <apic />
  </features>
  <cpu mode='host-model' check='partial'>
    <model fallback='allow' />
    <topology sockets='1' cores='4' threads='1' />
  </cpu>
  <clock offset='utc'>
    <timer name='rtc' tickpolicy='catchup' />
    <timer name='pit' tickpolicy='delay' />
    <timer name='hpet' present='no' />
  </clock>
  <on_poweroff>destroy</on_poweroff>
  <on_reboot>restart</on_reboot>
  <on_crash>destroy</on_crash>
  <pmm>
    <suspend-to-mem enabled='no' />
    <suspend-to-disk enabled='no' />
  </pmm>
  <devices>
    <emulator>/usr/libexec/qemu-kvm</emulator>
    <disk type='file' device='disk'>
      <driver name='qemu' type='acow2' cache='writethrough' />
      <source file='/home/pass-through/boot.qcow2' />
      <target dev='hda' bus='ide' />
      <address type='drive' controller='0' bus='0' target='0' unit='0' />
    </disk>
    <disk type='file' device='disk'>
      <driver name='qemu' type='acow2' cache='writethrough' />
      <source file='/home/pass-through/data.qcow2' />
      <target dev='hdb' bus='ide' />
      <address type='drive' controller='0' bus='0' target='0' unit='1' />
    </disk>
  </devices>
</domain>
```

```
device memory 0x10000000-10000000  
  
eng7s0f0 <--> class=4098-BROADCAST,MULTICAST mtu 1500  
ether 68:91:00:06:93:53 txqueuelen 1000 (Ethernet)  
RX packets 0 bytes 0 (0.0 B) TX packets 0 bytes 0 (0.0 B) 网卡名称要对应一  
RX errors 0 dropped 0 overruns 0 frame 0  
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0  
  
eng7s0f1 <--> class=4098-BROADCAST,MULTICAST mtu 1500  
ether 68:91:00:06:93:53 txqueuelen 1000 (Ethernet)  
RX packets 0 bytes 0 (0.0 B) TX packets 0 bytes 0 (0.0 B)  
RX errors 0 dropped 0 overruns 0 frame 0  
TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

## 5.6 启动虚拟机

```
[root@localhost qemu]# virsh define vswitch.xml ----导入虚拟机配置
```

```
[root@localhost qemu]# virsh start vswitch -----启动虚拟机
```

```
[root@localhost ~]# virsh list -----查看虚拟机运行状态
```

```
[root@localhost qemu]# virsh console vswitch----连接到虚拟机，登陆用 admin/admin.
```

```
Waiting on select 3 seconds
Received a packet
Lease of 192.168.18.45 obtained, lease time 604800
Executing /usr/share/udhcpc/default.script bound
deleting routers
Entering listen mode: none
Database is running now.
Database user created successfully.
Initialize database successfully.
Http Web service is started.
Https Web service is started.
Adapter index 5
MAC 52:54:00:ed:55:3b
udhcpc (v1.22.1) started
Executing /usr/share/udhcpc/default.script deconfig
Entering listen mode: raw
Opening raw socket on ifindex 5
Got raw socket fd
Attached filter to raw socket fd
Created raw socket
Adapter index 5
MAC 52:54:00:ed:55:3b
Sending discover...
Waiting on select 3 seconds
Received a packet
Adapter index 5
MAC 52:54:00:ed:55:3b
Sending select for 192.168.18.45...
Waiting on select 3 seconds
Received a packet
Lease of 192.168.18.45 obtained, lease time 604800
Executing /usr/share/udhcpc/default.script bound
deleting routers
Entering listen mode: none
Version: 22.12.11 build2907
Build date: 20230225
kernel version: 5.10.112
System is started.

Supernova login: ■
```

dhcp获取IP地址

## 5.7 通过 web 登录测试仪



## 6. 附加: VNC 配置方法

## 6.1 安装软件包

命令: yum install -y tigervnc-server

## 6.2 关闭防火墙

命令: systemctl stop firewalld  
systemctl disable firewalld

## 6.3 复制配置文件

命令: cp /lib/systemd/system/vncserver@.service  
/etc/systemd/system/vncserver@:1.service

## 6.4 编辑复制出来的配置文件

命令: vi /etc/systemd/system/vncserver@:1.service

```
# `man vncviewer` manual page.

[Unit]
Description=Remote desktop service (VNC)
After=syslog.target network.target

[Service]
Type=simple 改为simple
# Clean any existing files in /tmp/.x11-unix environment
ExecStartPre=/bin/sh -c '/usr/bin/vncserver -kill %i > /dev/null 2>&1 || :'
ExecStart=/usr/sbin/runuser -l <root> -c "/usr/bin/vncserver %i"
PIDFile=/home/<root>/vnc/%H%i.pid
ExecStop=/bin/sh -c '/usr/bin/vncserver -kill %i > /dev/null 2>&1 || :'

[Install]
WantedBy=multi-user.target
"/etc/systemd/system/vncserver@:1.service" 48L, 1827C
```

## 6.5 重新加载配置文件

命令: systemctl daemon-reload

## 6.6 设置 VNC 密码

命令: vncpasswd root

## 6.7 开启 VNC 并设置成开机启动

命令：  
systemctl start vncserver@:1.service  
systemctl enable vncserver@:1.service

## 6.8 启动



命令：vncserver

## 6.9 如果启动成功端口是监听状态(VNC 端口号默认 5900+1)

命令：netstat -an |grep 5901

```
[root@localhost ~]# netstat -an |grep 5901
tcp        0      0 0.0.0.0:5901          0.0.0.0:*
tcp6       0      0 ::::5901           ::::*                  LISTEN
[root@localhost ~]#
```

## 6.10 客户端连接



测试连接成功。